

Konfiguracja usług dla systemów Windows 7 SP1

Nazwa usługi (Rejestr)	Bezpieczne wyłączenie usług (zalecane)	Zaawansowane wyłączenie usług (dla zaawansowanych)	Twarde wyłączenie usług (niezalecane)
AxInstSV	Manual	Disabled *	Disabled *
SensrSvc	Manual	Disabled *	Disabled *
AeLookupSvc	Manual	Manual	Manual
AppHostSvc	Not Installed	Not Installed	Not Installed
AppIDSvc	Manual	Manual	Manual
Appinfo	Manual	Manual	Manual
ALG	Manual	Disabled *	Disabled *
AppMgmt	Disabled *	Disabled *	Disabled *
aspnet_state	Not Installed	Not Installed	Not Installed
BITS	Manual	Manual	Disabled *
BFE	Automatic	Automatic	Disabled *
BDESVC	Manual	Disabled *	Disabled *
wbengine	Manual	Manual	Disabled *
bthserv	Disabled *	Disabled *	Disabled *
PeerDistSvc	Disabled *	Disabled *	Disabled *
CertPropSvc	Disabled *	Disabled *	Disabled *
NfsClnt	Not Installed	Not Installed	Not Installed
KeyIso	Manual	Manual	Disabled *
EventSystem	Automatic	Automatic	Automatic
COMSysApp	Manual	Manual	Manual
Browser	Manual	Manual	Manual
VaultSvc	Manual	Disabled *	Disabled *
CryptSvc	Automatic	Automatic	Automatic
DcomLaunch	Automatic	Automatic	Automatic
UxSms	Automatic	Automatic	Disabled *
Dhcp	Automatic	Automatic	Automatic
DPS	Automatic	Disabled *	Disabled *
WdiServiceHost	Manual	Disabled *	Disabled *
WdiSystemHost	Manual	Disabled *	Disabled *
defragsvc	Manual	Manual	Manual
TrkWks	Disabled *	Disabled *	Disabled *
MSDTC	Manual	Manual	Manual
Dnscache	Automatic	Automatic	Disabled *
EFS	Manual	Disabled *	Disabled *
EapHost	Manual	Manual	Disabled *
Fax	Manual	Disabled *	Uninstalled *
fdPHost	Manual	Disabled *	Disabled *
FDResPub	Automatic	Disabled *	Disabled *
gpsvc	Automatic	Automatic	Automatic
hkmsvc	Manual	Disabled *	Disabled *
HomeGroupListener	Manual	Manual	Disabled *
HomeGroupProvider	Manual	Manual	Disabled *
hidserv	Manual	Disabled *	Disabled *
IISADMIN	Not Installed	Not Installed	Not Installed
IKEEXT	Manual	Manual	Disabled *
CISVC	Not Installed	Not Installed	Not Installed
UIODetect	Manual	Disabled *	Disabled *
SharedAccess	Disabled	Disabled	Disabled

iphlpvc	Disabled *	Disabled *	Disabled *
PolicyAgent	Manual	Manual	Disabled *
KtmRm	Manual	Manual	Manual
ltdsvc	Manual	Disabled *	Disabled *
LPDSVC	Not Installed	Not Installed	Not Installed
Mcx2Svc	Disabled	Disabled	Uninstalled *
MSMQ	Not Installed	Not Installed	Not Installed
MSMQTriggers	Not Installed	Not Installed	Not Installed
clr_optimization_v2.0.50727	Manual	Manual	Manual
ftpsvc	Not Installed	Not Installed	Not Installed
MSiSCSI	Disabled *	Disabled *	Disabled *
swprv	Manual	Manual	Manual
MMCSS	Automatic	Automatic	Automatic
NetMsmqActivator	Not Installed	Not Installed	Not Installed
NetPipeActivator	Not Installed	Not Installed	Not Installed
NetTcpActivator	Not Installed	Not Installed	Not Installed
NetTcpPortSharing	Disabled	Disabled	Uninstalled *
Netlogon	Disabled *	Disabled *	Disabled *
napagent	Disabled *	Disabled *	Disabled *
Netman	Manual	Manual	Manual
netprofm	Manual	Manual	Manual
NlaSvc	Automatic	Automatic	Automatic
nsi	Automatic	Automatic	Automatic
CscService	Disabled *	Disabled *	Disabled *
WPCCSvc	Disabled *	Disabled *	Disabled *
PNRPsvc	Manual	Disabled *	Disabled *
p2psvc	Manual	Disabled *	Disabled *
p2pimsvc	Manual	Disabled *	Disabled *
pla	Manual	Manual	Manual
PlugPlay	Automatic	Automatic	Automatic
IPBusEnum	Manual	Disabled *	Disabled *
PNRPAutoReg	Manual	Disabled *	Disabled *
WPDBusEnum	Manual	Disabled *	Disabled *
Power	Automatic	Automatic	Automatic
Spooler	Automatic	Automatic	Automatic
wercplsupport	Manual	Disabled *	Disabled *
PcaSvc	Manual	Disabled *	Disabled *
ProtectedStorage	Manual	Manual	Manual
QWAVE	Manual	Disabled *	Disabled *
RasAuto	Manual	Manual	Manual
RasMan	Manual	Manual	Manual
SessionEnv	Manual	Disabled *	Disabled *
TermService	Manual	Disabled *	Disabled *
UmRdpService	Manual	Disabled *	Disabled *
RpcSs	Automatic	Automatic	Automatic
RpcLocator	Disabled *	Disabled *	Disabled *
RemoteRegistry	Disabled *	Disabled *	Disabled *
iprip	Not Installed	Not Installed	Not Installed
RemoteAccess	Disabled	Disabled	Disabled
RpcEptMapper	Automatic	Automatic	Automatic

SeaPort	Not Installed	Not Installed	Not Installed
seclogon	Manual	Manual	Manual
SstpSvc	Manual	Manual	Disabled *
SamSs	Automatic	Automatic	Automatic
wscsvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Disabled *
LanmanServer	Automatic	Automatic	Automatic
ShellHWDetection	Automatic	Automatic	Automatic
simptcp	Not Installed	Not Installed	Not Installed
SCardSvr	Disabled *	Disabled *	Disabled *
SCPolicySvc	Disabled *	Disabled *	Disabled *
SNMP	Not Installed	Not Installed	Not Installed
SNMPTRAP	Disabled *	Disabled *	Disabled *
sppsvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
sppuinotify	Manual	Manual	Manual
SSDPSRV	Manual	Manual	Manual
StorSvc	Disabled *	Disabled *	Disabled *
SysMain	Automatic	Automatic	Automatic
SENS	Automatic	Automatic	Automatic
TabletInputService	Manual	Disabled *	Disabled *
Schedule	Automatic	Automatic	Automatic
lmhosts	Automatic	Automatic	Disabled *
TapiSrv	Manual	Manual	Disabled *
TlntSvr	Not Installed	Not Installed	Not Installed
Themes	Automatic	Automatic	Disabled *
THREADORDER	Manual	Manual	Manual
TBS	Manual	Disabled *	Disabled *
upnphost	Manual	Manual	Manual
ProfSvc	Automatic	Automatic	Automatic
vds	Manual	Manual	Manual
VSS	Manual	Manual	Manual
WMSVC	Not Installed	Not Installed	Not Installed
WebClient	Manual	Disabled *	Disabled *
AudioSrv	Automatic	Automatic	Automatic
AudioEndpointBuilder	Automatic	Automatic	Automatic
SDRSVC	Manual	Manual	Manual
WbioSrv	Manual	Disabled *	Disabled *
idsvc	Manual	Disabled *	Uninstalled *
WcsPlugInService	Manual	Disabled *	Disabled *
wcncsvc	Disabled *	Disabled *	Disabled *
WinDefend	Automatic (Delayed Start)	Automatic (Delayed Start)	Disabled *
wudfsvc	Manual ****	Manual ****	Manual ****
WerSvc	Manual	Disabled *	Disabled *
Weccsvc	Manual	Manual	Manual
EventLog	Automatic	Automatic	Automatic
MpsSvc	Automatic	Automatic	Disabled *
FontCache	Automatic (Delayed Start, Started) ****	Automatic (Delayed Start, Started) ****	Automatic (Delayed Start, Started) ****
StiSvc	Manual	Manual	Manual
msiserver	Manual	Manual	Manual
fssvc	Not Installed	Not Installed	Not Installed
Winmgmt	Automatic	Automatic	Automatic

ehRecvr	Manual	Disabled *	Uninstalled *
ehSched	Manual	Disabled *	Uninstalled *
WMPNetworkSvc	Disabled *	Disabled *	Uninstalled *
TrustedInstaller	Manual	Manual	Manual
FontCache3.0.0.0	Manual	Manual	Uninstalled *
WAS	Not Installed	Not Installed	Not Installed
WinRM	Manual	Disabled *	Disabled *
WSearch	Disabled *	Disabled *	Uninstalled *
W32Time	Manual	Manual	Disabled *
wuauserv	Automatic (Delayed Start)	Automatic (Delayed Start)	Disabled *
WinHttpAutoProxySvc	Manual	Disabled *	Disabled *
dot3svc	Manual	Manual	Disabled *
Wlansvc	Manual	Manual	Disabled *
wmiApSrv	Manual	Manual	Manual
LanmanWorkstation	Automatic	Automatic	Automatic
W3SVC	Not Installed	Not Installed	Not Installed
WwanSvc	Manual	Disabled *	Disabled *

LEGENDA:

Jedna * (gwiazdka) informuje o tym, iż ustawienia domyślne usługi zostały zmienione

Dwie ** (gwiazdki) informują, iż usługi mogą zostać wyłączone przez odinstalowanie dodatkowych funkcji systemu z poziomu Panelu Sterowania

Trzy *** (gwiazdki) oznaczają usługi zainstalowane przez program Windows Live Essentials

Cztery **** (gwiazdki) oznaczają zmiany usług w porównaniu do edycji SP0 (RTM) Windows 7

Automatic (usługa uruchamiana automatycznie), w rejestrze oznacza cyfrę: **2**

Manual (usługa wyłączona ręcznie), w rejestrze oznacza cyfrę: **3**

Disabled (usługa wyłączona), w rejestrze oznacza cyfrę: **4**

Not installed (usługa nie zainstalowana)