

### Konfiguracja usług dla systemów Windows 8/8.1

Nazwa usługi (rejestr):	Ustawienia bezpieczne
AxInstSV	Manual
AppReadiness	Manual
AeLookupSvc	Manual
AppHostSvc	Not Installed
AppIDSvc	Manual
Appinfo	Manual
ALG	Manual
AppXSVC	Manual
AppMgmt	Disabled *
aspnet_state	Not Installed
BITS	Automatic (Delayed Start)
BrokerInfrastructure	Automatic
BFE	Automatic
BDESVC	Manual
wbengine	Manual
bthserv	Disabled *
PeerDistSvc	Disabled *
CertPropSvc	Disabled *
c2wts	Not Installed
NfsClnt	Disabled *
KeyIso	Manual
EventSystem	Automatic
COMSysApp	Manual
Browser	Manual
VaultSvc	Manual
CryptSvc	Automatic
DcomLaunch	Automatic
DeviceAssociationService	Automatic
DeviceInstall	Manual
DsmSVC	Manual
Dhcp	Automatic
DPS	Automatic
WdiServiceHost	Manual
WdiSystemHost	Manual
TrkWks	Disabled *
MSDTC	Manual
Dnscache	Automatic
DsRoleSvc	Not installed
EFS	Manual
EapHost	Manual
WPCSvc	Disabled *
Fax	Manual
fhsvc	Manual

fdPHost	Manual
FDResPub	Manual
gpsvc	Automatic
hkmsvc	Manual
HomeGroupListener	Manual
HomeGroupProvider	Manual
hidserv	Manual
vmickvpexchange	Disabled *
vmicguestinterface	Disabled *
vmicshutdown	Disabled *
vmicheartbeat	Disabled *
vmicrdv	Disabled *
vmictimesync	Disabled *
vmicvss	Disabled *
IISADMIN	Not Installed
IKEEXT	Manual
UIODetect	Manual
SharedAccess	Disabled
IEEtwCollectorService	Disabled *
iphlpvc	Disabled *
PolicyAgent	Manual
KtmRm	Manual
lltdsvc	Manual
LSM	Automatic
LPDSVC	Not Installed
MSMQTriggers	Not Installed
MSMQ	Not Installed
wlidsvc	Manual
ftpsvc	Not Installed
MSiSCSI	Disabled *
swprv	Manual
MMCSS	Automatic
NetMsmqActivator	Not Installed
NetPipeActivator	Not Installed
NetTcpActivator	Not Installed
NetTcpPortSharing	Uninstalled *
Netlogon	Disabled *
napagent	Disabled *
NcdAutoSetup	Manual
NcbService	Manual
Netman	Manual
NcaSVC	Manual
netprofm	Manual
NlaSvc	Automatic
nsi	Automatic
CscService	Disabled *
defragsvc	Manual
PNRPsvc	Manual

p2psvc	Manual
p2pimsvc	Manual
pla	Manual
PlugPlay	Manual
PNRPAutoReg	Manual
WPDBusEnum	Manual
Power	Automatic
Spooler	Automatic
PrintNotify	Manual
wercplsupport	Manual
PcaSvc	Automatic
QWAVE	Manual
RasAuto	Manual
RasMan	Manual
SessionEnv	Manual
UmRdpService	Manual
TermService	Manual
RpcSs	Automatic
RpcLocator	Disabled *
RemoteRegistry	Disabled
iprip	Not Installed
RemoteAccess	Disabled
RpcEptMapper	Automatic
seclogon	Manual
SstpSvc	Manual
SamSs	Automatic
wscsvc	Automatic (Delayed Start)
SensrSvc	Disabled *
LanmanServer	Automatic
ShellHWDetection	Automatic
simptcp	Not Installed
SCardSvr	Disabled
ScDeviceEnum	Disabled *
SCPolicySvc	Disabled *
SNMP	Not Installed
SNMPTRAP	Disabled *
sppsvc	Automatic (Delayed Start)
svsvc	Manual
SSDPSRV	Manual
WiaRpc	Manual
StorSvc	Disabled *
SysMain	Automatic
SENS	Automatic
SystemEventsBroker	Automatic
Schedule	Automatic
lmhosts	Automatic
TapiSrv	Manual
TlntSvr	Not Installed

Themes	Automatic
THREADORDER	Manual
TimeBroker	Manual
TabletInputService	Manual
upnphost	Manual
ProfSvc	Automatic
vds	Manual
VSS	Manual
WMSVC	Not Installed
WebClient	Manual
AudioSrv	Automatic
AudioEndpointBuilder	Automatic
WbioSrv	Disabled *
WcsPlugInService	Manual
wcncsvc	Disabled *
Wcmsvc	Automatic
WdNisSvc	Manual
WinDefend	Automatic
wudfsvc	Manual
WEPHOSTSVC	Manual
WerSvc	Manual
Weccsvc	Manual
EventLog	Automatic
MpsSvc	Automatic
FontCache	Automatic
StiSvc	Manual
msiserver	Manual
lfsvc	Disabled *
Winmgmt	Automatic
WMPNetworkSvc	Disabled * (Uninstalled)
TrustedInstaller	Manual
FontCache3.0.0.0	Not Installed
WAS	Not Installed
WinRM	Manual
WSearch	Automatic (Delayed Start)
WSService	Manual
W32Time	Manual
wuauerv	Manual
WinHttpAutoProxySvc	Manual
dot3svc	Manual
WlanSvc	Manual
wmiApSrv	Manual
workfoldersvc	Manual
LanmanWorkstation	Automatic
W3SVC	Not Installed
WwanSvc	Manual

**LEGENDA:**

**Jedna \*** (gwiazdka) informuje o tym, iż ustawienia domyślne usługi zostały zmienione

**Automatic** (usługa uruchamiana automatycznie), w rejestrze oznacza cyfrę: **2**

**Manual** (usługa wyłączona ręcznie), w rejestrze oznacza cyfrę: **3**

**Disabled** (usługa wyłączona), w rejestrze oznacza cyfrę: **4**

**Not installed** (usługa nie zainstalowana)