

### Konfiguracja usług dla systemu Windows 10:

Nazwa usługi (rejestr):	Bezpieczne ustawienia dla komputera	Bezpieczne ustawienia dla laptopa i tabletu:	Zaawansowane ustawienia dla komputera
AxInstSV	Manual	Manual	Manual
AJRouter	Manual	Manual	Disabled *
AppReadiness	Manual	Manual	Manual
AppHostSvc	Not Installed	Not Installed	Not Installed
AppIDSvc	Manual	Manual	Manual
Appinfo	Manual	Manual	Manual
ALG	Disabled *	Disabled *	Disabled *
AppMgmt	Manual	Manual	Disabled *
AppXSVC	Manual	Manual	Manual
AssignedAccessManagerSvc	Manual	Manual	Manual
aspnet_state	Not Installed	Not Installed	Not Installed
tzautoupdate	Disabled	Disabled	Disabled
BthAvctpSvc	Manual (Trigger Start)	Manual (Trigger Start)	Disabled *
BITS	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
BrokerInfrastructure	Automatic	Automatic	Automatic
BFE	Automatic	Automatic	Automatic
BDESVC	Manual	Manual	Manual
wbengine	Manual	Manual	Manual
BTAGService	Manual	Manual	Disabled *
bthserv	Manual	Manual	Disabled *
BluetoothUserService_?????	Manual	Manual	Manual
PeerDistSvc	Disabled *	Disabled *	Disabled *
camsvc	Manual	Manual	Manual
CaptureService_?????	Manual	Manual	Disabled *
CertPropSvc	Manual	Manual	Disabled *
c2wts	Not Installed	Not Installed	Not Installed
NfsClnt	Disabled *	Disabled *	Disabled *
ClipSVC	Manual	Manual	Manual
KeyIso	Manual	Manual	Manual
EventSystem	Automatic	Automatic	Automatic
COMSysApp	Manual	Manual	Manual
Browser	Manual	Manual	Manual
CDPSvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
CDPUserSvc_?????	Automatic	Automatic	Automatic
DiagTrack	Automatic	Automatic	Automatic
PimIndexMaintenanceSvc_?????	Manual	Manual	Manual
CoreMessagingRegistrar	Automatic	Automatic	Automatic
VaultSvc	Manual	Manual	Manual
CryptSvc	Automatic	Automatic	Automatic
DsSvc	Manual	Manual	Manual
DusmSvc	Automatic	Automatic	Automatic
DcomLaunch	Automatic	Automatic	Automatic
DoSvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
DeviceAssociationService	Manual	Manual	Manual
DeviceInstall	Manual	Manual	Manual
DmEnrollmentSvc	Manual	Manual	Manual
DsmSVC	Manual	Manual	Manual

DevicePickerUserSvc_?????	Manual	Manual	Manual
DevicesFlowUserSvc_?????	Manual	Manual	Manual
DevQueryBroker	Manual	Manual	Manual
Dhcp	Automatic	Automatic	Automatic
diagsvc	Manual	Manual	Manual
DPS	Automatic	Automatic	Automatic
WdiServiceHost	Manual	Manual	Manual
WdiSystemHost	Manual	Manual	Manual
TrkWks	Automatic	Automatic	Automatic
MSDTC	Manual	Manual	Manual
dmwappushsvc	Disabled *	Disabled *	Disabled *
Dnscache	Automatic	Automatic	Automatic
MapsBroker	Disabled *	Disabled *	Disabled *
DsRoleSvc	Not installed	Not installed	Not installed
embeddedmode	Manual	Manual	Manual
EFS	Manual	Manual	Manual
EntAppSvc	Manual	Manual	Manual
EapHost	Manual	Manual	Manual
Fax	Uninstalled *	Uninstalled *	Uninstalled *
fhsvc	Manual	Manual	Manual
fdPHost	Manual	Manual	Manual
FDResPub	Manual	Manual	Manual
BcastDVRUserService_?????	Manual	Manual	Manual
lfsvc	Disabled *	Disabled *	Disabled *
GraphicsPerfSvc	Manual	Manual	Manual
gpsvc	Automatic	Automatic	Automatic
hns	Not Installed	Not Installed	Not Installed
hidserv	Manual	Manual	Manual
HvHost	Disabled *	Disabled *	Disabled *
vmickvpexchange	Disabled *	Disabled *	Disabled *
vmicguestinterface	Disabled *	Disabled *	Disabled *
vmicshutdown	Disabled *	Disabled *	Disabled *
vmicheartbeat	Disabled *	Disabled *	Disabled *
vmcompute	Not Installed	Not Installed	Not Installed
vmicvmsession	Disabled *	Disabled *	Disabled *
vmicrdv	Disabled *	Disabled *	Disabled *
vmictimesync	Disabled *	Disabled *	Disabled *
vmms	Not Installed	Not Installed	Not Installed
vmicvss	Disabled *	Disabled *	Disabled *
IISADMIN	Not Installed	Not Installed	Not Installed
IKEEXT	Manual	Manual	Manual
irmon	Disabled *	Disabled *	Disabled *
UIODetect	Manual	Manual	Manual
SharedAccess	Disabled *	Disabled *	Disabled *
iphlpvc	Automatic	Automatic	Disabled *
IpxlatCfgSvc	Manual	Manual	Disabled *
PolicyAgent	Manual	Manual	Manual
KtmRm	Manual	Manual	Manual
lltdsvc	Manual	Manual	Manual
wlpassvc	Manual	Manual	Manual

LSM	Automatic	Automatic	Automatic
LPDSVC	Not Installed	Not Installed	Not Installed
LxssManager	Not Installed	Not Installed	Not Installed
MSMQ	Not Installed	Not Installed	Not Installed
MSMQTriggers	Not Installed	Not Installed	Not Installed
MessagingService_?????	Manual	Manual	Manual
diagnosticshub.standardcollector.service	Manual	Manual	Manual
wlidsvc	Manual	Manual	Manual
AppVClient	Disabled	Disabled	Disabled
ftpsvc	Not Installed	Not Installed	Not Installed
MSiSCSI	Disabled *	Disabled *	Disabled *
MsKeyboardFilter	Not Installed	Not Installed	Not Installed
NgcSvc	Manual	Manual	Manual
NgcCtnrSvc	Manual	Manual	Manual
swprv	Manual	Manual	Manual
smphost	Manual	Manual	Manual
InstallService	Manual	Manual	Manual
SmsRouter	Disabled *	Disabled *	Disabled *
WmsRepair	Not Installed	Not Installed	Not Installed
Wms	Not Installed	Not Installed	Not Installed
NaturalAuthentication	Manual	Manual	Disabled *
NetMsmqActivator	Not Installed	Not Installed	Not Installed
NetPipeActivator	Not Installed	Not Installed	Not Installed
NetTcpActivator	Not Installed	Not Installed	Not Installed
NetTcpPortSharing	Uninstalled *	Uninstalled *	Uninstalled *
Netlogon	Manual	Manual	Disabled *
NcdAutoSetup	Manual	Manual	Disabled *
NcbService	Manual	Manual	Manual
Netman	Manual	Manual	Manual
NcaSVC	Manual	Manual	Manual
netprofm	Manual	Manual	Manual
NlaSvc	Automatic	Automatic	Automatic
NetSetupSvc	Manual	Manual	Manual
nsi	Automatic	Automatic	Automatic
CscService	Disabled *	Disabled *	Disabled *
ssh-agent	Manual	Manual	Manual
defragsvc	Manual	Manual	Manual
WpcMonSvc	Disabled *	Disabled *	Disabled *
SEMgrSvc	Disabled *	Disabled *	Disabled *
PNRPsvc	Manual	Manual	Manual
p2psvc	Manual	Manual	Manual
p2pimsvc	Manual	Manual	Manual
PerfHost	Manual	Manual	Manual
pla	Manual	Manual	Manual
PhoneSvc	Disabled *	Disabled *	Disabled *
PlugPlay	Manual	Manual	Manual
PNRPAutoReg	Manual	Manual	Manual
WPDBusEnum	Manual	Manual	Manual
Power	Automatic	Automatic	Automatic
Spooler	Automatic	Automatic	Automatic

PrintNotify	Manual	Manual	Manual
PrintWorkflowUserSvc_?????	Manual	Manual	Manual
wercplsupport	Manual	Manual	Manual
PcaSvc	Automatic	Automatic	Automatic
QWAVE	Manual	Manual	Manual
RmSvc	Manual	Manual	Manual
RasAuto	Manual	Manual	Manual
RasMan	Manual	Manual	Manual
SessionEnv	Manual	Manual	Disabled *
TermService	Manual	Manual	Disabled *
UmRdpService	Manual	Manual	Disabled *
RpcSs	Automatic	Automatic	Automatic
RpcLocator	Disabled *	Disabled *	Disabled *
RemoteRegistry	Disabled	Disabled	Disabled
RetailDemo	Disabled *	Disabled *	Disabled *
iprip	Not Installed	Not Installed	Not Installed
RemoteAccess	Disabled	Disabled	Disabled
RpcEptMapper	Automatic	Automatic	Automatic
seclogon	Manual	Manual	Manual
SstpSvc	Manual	Manual	Manual
SamSs	Automatic	Automatic	Automatic
wscsvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
SensorDataService	Disabled *	Manual	Disabled *
SensrSvc	Disabled *	Manual	Disabled *
SensorService	Disabled *	Manual	Disabled *
LanmanServer	Automatic	Automatic	Automatic
shpamsvc	Disabled	Disabled	Disabled
ShellHWDetection	Automatic	Automatic	Automatic
simptcp	Not Installed	Not Installed	Not Installed
SCardSvr	Disabled	Disabled	Disabled
ScDeviceEnum	Disabled *	Disabled *	Disabled *
SCPolicySvc	Disabled *	Disabled *	Disabled *
SNMP	Not Installed	Not Installed	Not Installed
SNMPTRAP	Disabled *	Disabled *	Disabled *
sppsvc	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
SharedRealitySvc	Manual	Manual	Manual
svsvc	Manual	Manual	Manual
SSDPSRV	Manual	Manual	Manual
StateRepository	Manual	Manual	Manual
WiaRpc	Manual	Manual	Manual
StorSvc	Manual	Manual	Manual
TieringEngineService	Manual	Manual	Manual
SysMain	Automatic	Automatic	Automatic
OneSyncSvc_?????	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
SENS	Automatic	Automatic	Automatic
SystemEventsBroker	Automatic	Automatic	Automatic
SgrmBroker	Automatic (Delayed Start, Running)	Automatic (Delayed Start, Running)	Automatic (Delayed Start, Running)
Schedule	Automatic	Automatic	Automatic
lmhosts	Manual	Manual	Manual
TapiSrv	Manual	Manual	Manual

Themes	Automatic	Automatic	Automatic
TimeBroker	Manual	Manual	Manual
TabletInputService	Disabled *	Manual	Disabled *
UwfServicingSvc	Not Installed	Not Installed	Not Installed
UsSvc	Manual	Manual	Manual
upnphost	Manual	Manual	Manual
UserDataSvc_?????	Manual	Manual	Manual
UnistoreSvc_?????	Manual	Manual	Manual
UevAgentService	Disabled	Disabled	Disabled
UserManager	Automatic	Automatic	Automatic
ProfSvc	Automatic	Automatic	Automatic
vds	Manual	Manual	Manual
VSS	Manual	Manual	Manual
W3LOGSVC	Not Installed	Not Installed	Not Installed
WalletService	Manual	Manual	Manual
WMSVC	Not Installed	Not Installed	Not Installed
	Manual	Manual	Manual
TokenBroker	Manual	Manual	Manual
WebClient	Manual	Manual	Disabled *
WFDSConSvc	Disabled *	Manual	Disabled *
AudioSrv	Automatic	Automatic	Automatic
AudioEndpointBuilder	Automatic	Automatic	Automatic
SDRSVC	Manual	Manual	Manual
WbioSrv	Manual	Manual	Manual
FrameServer	Disabled *	Disabled *	Disabled *
wcncsvc	Manual	Manual	Disabled *
WcmSvc	Automatic	Automatic	Automatic
Sense	Manual	Manual	Manual
WdNisSvc	Manual	Manual	Manual
WinDefend	Automatic	Automatic	Automatic
MpsSvc	Automatic	Automatic	Automatic
SecurityHealthService	Automatic	Automatic	Automatic
WEHOSTSVC	Manual	Manual	Manual
WerSvc	Manual	Manual	Manual
WeSvc	Manual	Manual	Manual
EventLog	Automatic	Automatic	Automatic
FontCache	Automatic	Automatic	Automatic
StiSvc	Manual	Manual	Manual
wisvc	Disabled *	Disabled *	Disabled *
msiserver	Manual	Manual	Manual
LicenseManager	Manual	Manual	Manual
Winmgmt	Automatic	Automatic	Automatic
WMPNetworkSvc	Disabled * (Uninstalled)	Disabled * (Uninstalled)	Disabled * (Uninstalled)
icssvc	Disabled *	Disabled *	Disabled *
TrustedInstaller	Manual	Manual	Manual
spectrum	Manual	Manual	Manual
FontCache3.0.0.0	Not Installed	Not Installed	Not Installed
WAS	Not Installed	Not Installed	Not Installed
WpnService	Automatic	Automatic	Automatic
WpnUserService_?????	Automatic	Automatic	Automatic

PushToInstall	Manual	Manual	Manual
WinRM	Disabled *	Disabled *	Disabled *
WSearch	Automatic (Delayed Start)	Automatic (Delayed Start)	Automatic (Delayed Start)
W32Time	Manual	Manual	Manual
wuauerv	Manual	Manual	Manual
WaaSMedicSvc	Manual	Manual	Manual
WinHttpAutoProxySvc	Manual	Manual	Manual
dot3svc	Manual	Manual	Manual
WlanSvc	Manual	Automatic	Manual
wmiApSrv	Manual	Manual	Manual
workfoldersvc	Uninstalled *	Uninstalled *	Uninstalled *
LanmanWorkstation	Automatic	Automatic	Automatic
W3SVC	Not Installed	Not Installed	Not Installed
WwanSvc	Disabled *	Disabled *	Disabled *
XboxGipSvc	Manual	Manual	Manual
xbgm	Manual	Manual	Manual
XblAuthManager	Disabled *	Disabled *	Disabled *
XblGameSave	Disabled *	Disabled *	Disabled *
XboxNetApiSvc	Disabled *	Disabled *	Disabled *

**LEGENDA:**

**Jedna \*** (gwiazdka) informuje o tym, iż ustawienia domyślne usługi zostały zmienione

**Automatic** (usługa uruchamiana automatycznie), w rejestrze oznacza cyfrę: 2

**Manual** (usługa wyłączona ręcznie), w rejestrze oznacza cyfrę: 3

**Disabled** (usługa wyłączona), w rejestrze oznacza cyfrę: 4

**Not installed** (usługa nie zainstalowana)

